
## **Learning Tools Interoperability**

School-Side LTI Setup Guide for Moodle LMS



Catalog # 34-8000-0011 Rev. A

NOVEMBER 2017





Copyright © 2017 Intelitek Inc.

Canvas LTI Setup Guide – School-Side

# 34-8000-0011 Rev. A

NOVEMBER 2017

Every effort has been made to make this guide complete and as accurate as possible. However, no warranty of suitability, purpose, or fitness is made or implied. Intelitek Inc. is not liable or responsible to any person or entity for loss or damage in connection with, or stemming from, the use of the software, equipment, and/or the information contained in this publication.

Intelitek Inc. bears no responsibility for errors which may appear in this publication and retains the right to make changes to the software, equipment and manual without prior notice.

Intelitek Inc.

Toll Free: 800-221-2763

Phone: 603-413-2600

Fax: 603-437-2137

Email: info@intelitek.com



## Contents


1. Learning Tools Interoperability	.4
2. School-Side Setup using Moodle LMS	.5



## 1. Learning Tools Interoperability

Learning Tools Interoperability (LTI) is a standard whose primary purpose is to connect learning management systems (LMS) with external service tools. This standard defines the connecting LMS as an LTI tool consumer and the connected system such as Intelitek LearnMate as an LTI tool provider.

Intelitek provides the school side with an access code called a 'Shared Secret', which allows the school access to specific Intelitek content.





## 2. School-Side Setup using Moodle LMS

To set up an external tool activity in order to access the learning tool of an LTI provider:

- 1. Enter the course in which you want to add the external tool.
- 2. In the top-right corner of the page, click **Turn editing on**.



3. In the desired topic or week, click **Add an activity or resource**.



4. In the Add an activity or resource window, select the **External tool** activity.



5. Click **Add** to create the activity.



You are automatically directed to the external tool settings page.

6. Under General settings, complete the **Activity** name field.






7. Click **Show more** to expand the rest of the general settings.



- 8. Complete the fields of the following settings:
  - Launch URL: This is the provider tool's URL. The URL is listed in the provider's
    List of tools provided page (See section 2.2 on page 5). This URL should be
    provided to you, the consumer, by the provider. It might be called "URL
    Cartridge."
  - **Consumer key**: This is a username to authenticate access to the tool. It is defined by you, the consumer.
  - **Shared secret**: This can be thought of as a password to authenticate the tool. The shared secret is defined by the provider when defining the settings for the tool and should be provided to you, the consumer.



9. Define the remainder of the settings as desired, and then click Save and return to course or Save and display to confirm.



The external tool is created and can be accessed by users on the course page.



Note: Users do not have to sign on to the provider's site when accessing the external tool.